

Cisco Jabber Client Install Instructions for Windows

External Users

Windows PC requirements:

- **Processor:** 2 GHz Core 2 Duo processor or better
- **Memory:** 1GB RAM or more
- **Operating System:** Windows 7 or Windows 8.x
- **IP network connection:** Broadband, LAN, wireless. At least 768 Kbps up and 1.5 Mbps down is highly recommended.
Please check with your ISP to determine your speed or visit <http://www.speedtest.net/>
- **Graphics Card:** OpenGL version 1.3 or OpenGL version 1.2 with the multitexturing extension.
- **Sound Card:** Any standard sound card (full-duplex, 16-bit or better) should work
- **Camera:** Designed to support all windows compatible web cameras
- **Microphone:** Is required. Most laptops have built-in microphone, however we recommend using the webcam's built-in mic (if available), as it provides better audio performance.


How to Install

(IMPORTANT: If you have a previous version of Jabber or Movi, please un-install it completely.)

1. Install the client on your Windows PC using the file attached to the email sent from Aspirus or from the public web site link below. <http://aspirus.org/Resource.ashx?sn=Jabber-Windows>
2. Select Run when Windows prompt you
3. Follow the installation instructions
4. Launch Cisco Jabber




1. Once launched, click the wrench/screwdriver icon to bring up the sign-in settings.














The image shows a screenshot of the 'Jabber Video' application's 'Sign-in Settings' dialog box. The dialog has a title bar with 'Jabber Video' and standard window controls. Inside, the 'Sign-in Settings' section contains two checked options: 'Start Jabber Video when I log on to my computer' and 'Sign in automatically'. Below this is a 'Servers' section with three input fields: 'Internal Server' (empty), 'External Server' (containing '71.13.116.126'), and 'SIP Domain' (containing 'aspirus.org'). At the bottom are 'OK' and 'Cancel' buttons.

2. Please fill in the Internal Server and SIP Domain fields with the above information, leave the internal server section blank and click OK.
 - a. External Server – 71.13.116.126
 - b. SIP Domain – aspirus.org
3. Once you click ok you will go back to the screen in the previous page. Please fill in the provided username and password provided to you in the email with the client install attachment.

4. Once you are logged in you will see the following screen.



5. You are now ready to receive video calls from Aspirus using Cisco Jabber. A toolbar with these buttons will appear when you move the mouse pointer over the video window during a call.

Icon	Controls	Description	Toggled
	Selfview	See yourself on camera. (See Controlling your camera [p.8].)	
	Camera	Turn your camera off/on. (See Controlling your camera [p.8].)	
	Microphone	Turn your microphone off/on.	
	Speaker volume	Click to mute, or drag slider to adjust.	
	Fullscreen	Use entire screen for video. You can also toggle this setting by double-clicking the video window.	
	Presentation sharing	Share an application window. (See Sharing presentations [p.9].)	
	End call	Hang up.	